
Bassoon Fingering Chart

Flick keys are drawn dashed where a key is touched only at the attack (A3, B♭3, B3, C4).


FIRST OCTAVE

B♭1




Left thumb low B♭ + B + C + D keys · left hand 1-2-3 · right thumb E key · right hand 1-2-3 · right pinky F key.

B1




Left thumb low B + C + D keys · left hand 1-2-3 · right thumb E key · right hand 1-2-3 · right pinky F key.

C2




Left thumb low C + D keys · left hand 1-2-3 · right thumb E key · right hand 1-2-3 · right pinky F key.

C♯2




Left thumb low C + D keys · left hand 1-2-3 · left pinky C♯ key · right thumb E key · right hand 1-2-3 · right pinky F key.

D2




Left thumb low D key · left hand 1-2-3 · right thumb E key · right hand 1-2-3 · right pinky F key.

E♭2




Left thumb low D key · left hand 1-2-3 · left pinky E♭ key · right thumb E key · right hand 1-2-3 · right pinky F key.

E2




Whisper key · left hand 1-2-3 · right thumb E key · right hand 1-2-3 · right pinky F key.

F2



Whisper key · left hand 1-2-3 · right hand 1-2-3 · right pinky F key.


F♯2



Whisper key · left hand 1-2-3 · right thumb F♯ key · right hand 1-2-3 · right pinky F key.


Also used: Whisper key · left hand 1-2-3 · right hand 1-2-3 · right pinky F key + F♯ key.

G2



Whisper key · left hand 1-2-3 · right hand 1-2-3.


G♯2



Whisper key · left hand 1-2-3 · right hand 1-2-3 · right pinky G♯ key.


Also used: Whisper key · left hand 1-2-3 · right thumb G♯ key · right hand 1-2-3.

A2



Whisper key · left hand 1-2-3 · right hand 1-2.


B♭2



Whisper key · left hand 1-2-3 · right thumb B♭ key · right hand 1-2.


Also used: Whisper key · left hand 1-2-3 · right hand 1-2 · sliver B♭ key.

B2




Whisper key · left hand 1-2-3 · right hand 1.

C3




Whisper key · left hand 1-2-3.

C♯3




Whisper key · left thumb low D key · left thumb C♯ key · left hand 1-2-3.

D3



Whisper key · left hand 1-2.


E♭3



Whisper key · left hand 1-3 · left pinky E♭ key.


Also used: Whisper key · left hand 1-3 · left pinky E♭ key · right thumb B♭ key · right hand 2.

E3



Whisper key · left hand 1.


F3



Whisper key.

SECOND OCTAVE


F♯3



Whisper key · left hand 1 (quarter-covered)-2-3 · right thumb F♯ key · right hand 1-2-3 · right pinky F key.


Also used: Whisper key · left hand 1 (quarter-covered)-2-3 · right hand 1-2-3 · right pinky F key + F♯ key.

G3



Whisper key · left hand 1 (half-covered)-2-3 · left pinky E♭ key · right hand 1-2-3.


G♯3



Whisper key · left hand 1 (three-quarter-covered)-2-3 · right hand 1-2-3 · right pinky G♯ key.


Also used: Whisper key · left hand 1 (three-quarter-covered)-2-3 · right thumb G♯ key · right hand 1-2-3.

A3



Flick the A key as the note starts · left hand 1-2-3 · right hand 1-2.


B♭3



Flick the B key as the note starts · left hand 1-2-3 · right thumb B♭ key · right hand 1-2.


Also used: Flick the B key as the note starts · left hand 1-2-3 · right hand 1-2 · sliver B♭ key.

B3




Flick the B key as the note starts · left hand 1-2-3 · right hand 1.

C4



Flick the B key as the note starts · left hand 1-2-3.


C♯4



Left thumb low D key · left thumb C♯ key · left hand 1-2-3.


Also used: Left thumb C♯ key · left hand 1-2-3 · right hand 2-3 · right pinky F key.

D4



Left hand 1-2.


E♭4



Left hand 1-2 · right hand 2-3.


Also used: Left hand 1-2 · right hand 1-2-3.

E4



Left hand 1-3 · left pinky E♭ key · right hand 1-2-3.


F4



Left hand 1-3 · left pinky E♭ key · right hand 1-2.


THIRD OCTAVE

F♯4




Left hand 2-3 · left pinky E♭ key · right hand 1-2 · right pinky F key.

G4




Whisper key · left hand 1 (half-covered)-2-3 · left pinky E♭ key · right hand 1 · right pinky F key.

G♯4



Left hand 1 (three-quarter-covered)-2-3 · left pinky E♭ key · right hand 3.


A4



Left thumb C♯ key · A flick key held down · left hand 1-2-3 · left pinky E♭ key · right hand 3.

Also used: Left hand 2-3 · left pinky E♭ key · right thumb B♭ key · right hand 1-2.

B♭4



Left thumb C♯ key · A flick key held down · left hand 1-2-3 · left pinky E♭ key · right hand 1-2 · right pinky F key.